

DMS3 oxs-office-server v3.0.0

Global Environment Variables

	Environment Variable Name	Description	Default / Example value
	NODE_ENV	Node Environment	production
	OXS_SERVER_CONFDIR	Root directory of server configuration files. When starting the server, it will look for its configuration files into the <OXS_SERVER_CONFDIR>/conf/<server name> directory. Ex: /usr/lib/node_modules//usr/lib/node_modules/oxs-office-server/conf/oxs-office-server/	/usr/lib/node_modules

processes.config.js Environment Variables

	Environment Variable Name	Description	Default Value
Server Level Environment Variables			
	UV_THREADPOOL_SIZE	Size of the threads pool	64
	OXSNPS_SERVER_PREFIX	OXSNPS Server Name Prefix	OXS_OFFICE_
	OXS_OFFICE_LOG_LEVEL	OXSNPS Server Log Level	INFO
	OXS_OFFICE_PORT	OXSNPS Server Port	1075
	OXS_OFFICE_LOGS_PATH	OXSNPS Servers Log Directory A sub directory <servername>/<hostname> is created within this root directory Log files are placed in .<servername>/<hostname> directory.	"/mnt/logs/" + appname + "/" + exports.getHostname(),
	OXS_OFFICE_TRANSFER_WORK_PATH	Root directory for creating working directories. A sub directory <servername>/<hostname> is created within this root directory. When processing the requests. for each request a sub directory <request id> is created within <servername>/<hostname>. This directory is shared between stateless servers and import servers	"/mnt/tmp/" + appname + "/" + exports.getHostname(),
	OXS_OFFICE_ENV_NAME	Environment name (production, integration...)	["production"]
	OXS_OFFICE_ENV_DISABLE_SWAGGER	Specifies the array of environments for which swagger API should be disabled	['production']
	OXS_OFFICE_STOP_ON_INIT_ERRORS	true false. Defaultl is true. When true, stop the server after logging the server statup error. When false, do not stop the server, log the server statup errors and proceed to load other plugins and modules	TRUE

	OXS_OFFICE_TRANSFER_WORK_PATH_CLEAN_CRON_TIME	Cron job time to clean work directories. Default is to run at 0th minute of every hour. Refer to https://github.com/kelektiv/node-cron/blob/master/README.md	00 00 * * * *
	OXS_OFFICE_TRANSFER_WORK_PATH_EXPIRY_PERIOD	Specifies the "time to live" in minutes for work directories and files. Default is to delete files that are older than 30 minutes.	30
	OXS_OFFICE_LOG_SERVER_ALIVE_STATUS	Cron job options to log server alive status	{"logLevel": "info", "cronTime": "0 0 * * * *", "message": "Server is running for ' + (days > 0 ? days + ' days, ' : ') + (hours > 0 ? hours + ' hours, ' : ') + minutes + ' minutes and ' + seconds + ' seconds'"}
Plugin Log Level Environment Variables			
	OXS_OFFICE_LOG_LEVEL_OXSNPS_ASSERT	oxsnps-assert log level	WARN
	OXS_OFFICE_LOG_LEVEL_OXSNPS_OFFICE2ANY	oxsnps-office log level	WARN
	OXS_OFFICE_LOG_LEVEL_OXSNPS_SPAWN	oxsnps-spawn log level	WARN